Setup:

- 1) Download and extract required files: **Download Link**
- 2) Navigate to the ServerCode folder and find the code for the type of Arduino you are using. (only Arduino Uno is supported so far). Open the .ino file in the Arduino IDE.
 Download the Arduino IDE here.

Upload the code to your Arduino.

Connecting to the Arduino from MATLAB:

- 1) All the required MATLAB code is contained in /Client Code/MATLAB/Arduino.m. Copy this file into your working directory.
- 2) Create a new Arduino object using the constructor: Arduino (port), and connect using Arduino.connect().

```
>>> arduino = Arduino('COM7');
>>> arduino.connect();
Connected to Arduino Uno running server code by Nigel Bess: https://github.com/NigelBess/Arduino-Server
```

If MATLAB did not print the above message, make sure the Arduino has the correct server code by following the instructions in the **Setup** Section.

Arduino Functions:

Most functions require a pin parameter. This parameter can be either a string or an integer. Use integer for performance or string for readability.

	String Form	Integer Form
Digital Pin 0	D0	0
Digital Pin 1	D1	1
Digital Pin 2	D2	2
Digital Pin 3	D3	3
Digital Pin 4	D4	4
Digital Pin 5	D5	5

Digital Pin 6	D6	6
Digital Pin 7	D7	7
Digital Pin 8	D8	8
Digital Pin 9	D9	9
Digital Pin 10	D10	10
Digital Pin 11	D11	11
Digital Pin 12	D12	12
Digital Pin 13	D13	13
Analog Pin 0	A0	14
Analog Pin 1	A1	15
Analog Pin 2	A2	16
Analog Pin 3	A3	17
Analog Pin 4	A4	18
Analog Pin 5	A5	19

Arduino.pinMode(pin, type)

Sets up [pin] for use as [type]. [type] can be either output, input or input with pullup, which can be defined as a string or integer. Use integer for performance or string for readability.

	String Form	Integer Form
Input	INPUT	0
Output	OUTPUT	1
Input with Pullup	INPUT_PULLUP	2

More information on pin types: https://www.arduino.cc/en/Tutorial/DigitalPins

Arduino.digitalWrite(pin,state)

Writes [state] to [pin]. [state] can be 0 (low) or 1 (high). Requires [pin] to be set up using **Arduino.pinMode()**.

Arduino.analogWrite(pin,value)

Writes [value] to [pin]. [value] is a voltage between 0 and 5v. Requires [pin] to be set up using **Arduino.pinMode()**.

Note: Arduino UNO PWM output pins are D3, D5, D6, D9, D10 and D11. analogWrite will act as digitalWrite for other pins. Values greater than 2.5 will correspond to 1.

Arduino.digitalRead(pinNumber)

Returns the state of [pin], as 0 (low) or 1 (high). Requires [pin] to be set up using **Arduino.pinMode()**.

Arduino.analogRead(pin)

Returns the voltage at [pin].

Requires [pin] to be set up using Arduino.pinMode().

Arduino.attachServo(pin)

Sets up servo control at [pin].

Arduino.writeServo(pin,angle)

Writes angle (in degrees between 0 and 180) to servo at [pin]. Requires [pin] to be set up using **Arduino.attachServo()**.

Arduino.detachServo(pin)

Detaches servo at [pin], and frees up [pin] for other use.

Arduino.encoder(interruptPin,[optional]secondaryPin)

Sets up an encoder with channel A at [interruptPin] (must be D2 or D3), and channel B at [secondaryPin] (any other pin). Omitting [secondaryPin] will cause the encoder to behave as an incremental encoder, as opposed to a quadrature encoder.

Arduino.readEncoder(interruptPin)

Returns the count of the encoder at [interruptPin].

Requires [interruptPin] to be set up using **Arduino.encoder()**.

Arduino.resetEncoder(interruptPin)

Sets the count of encoder at [interruptPin] to zero.

Requires [interruptPin] to be set up using **Arduino.encoder()**.

Arduino.setEncoderDirection(interruptPin,direction)

Sets the direction in which encoder ticks are counted, depending on the value of the direction parameter.

Direction Value	Effect
0	Do not count ticks
1	Count ticks with normal polarity
2	Count ticks with opposite polarity

Arduino.detachEncoder(interruptPin)

Detaches the encoder at interruptPin, and frees up [interruptPin] for other use.

Arduino.checkConnection()

Used to make sure that the arduino is still connected. It doesn't make the arduino do anything, but will throw an error if the arduino disconnected.